NAME

INSTALL — Installation procedure for NetBSD/amiga.

CONTENTS

About this Document....1
What is NetBSD?....2
Changes Between The NetBSD 3.0 and 4.0 Releases....2
  Networking....2
  Filesystems....3
  Drivers....3
  Platforms....5
  Kernel subsystems....5
  Security....6
  Userland....6
  Components removed from NetBSD....7
The Future of NetBSD....8
Sources of NetBSD....8
NetBSD 4.0_RC2 Release Contents....9
  NetBSD/amiga subdirectory structure....10
  Miniroot file system....10
  Binary distribution sets....10
NetBSD/amiga System Requirements and Supported Devices....12
  Supported devices....12
Getting the NetBSD System on to Useful Media....14
Preparing your System for NetBSD installation....16
  Preparing your hard disk with HDToolBox....16
  Transferring the miniroot file system....18
Installing the NetBSD System....18
  Booting....19
  Once your kernel boots....19
Post installation steps....21
Upgrading a previously-installed NetBSD System....24
  Once your kernel boots....24
Compatibility Issues With Previous NetBSD Releases....25
  Issues affecting an upgrade from NetBSD 2.1 and older....25
  Issues affecting an upgrade from NetBSD 3.x releases.....26
Using online NetBSD documentation....26
Administrivia....27
Thanks go to....27
We are....28
Legal Mumbo-Jumbo....36
The End....40

DESCRIPTION

About this Document

This document describes the installation procedure for NetBSD 4.0_RC2 on the *amiga* platform. It is available in four different formats titled INSTALL.*ext*, where *.ext* is one of .ps, .html, .more, or .txt:

`.ps` PostScript.

`.html` Standard Internet HTML.

`.more` The enhanced text format used on UNIX-like systems by the `more`(1) and `less`(1) pager utility programs. This is the format in which the on-line *man* pages are generally presented.

`.txt` Plain old ASCII.

You are reading the *PostScript* version.

What is NetBSD?

The NetBSD Operating System is a fully functional Open Source UNIX-like operating system derived from the University of California, Berkeley Networking Release 2 (Net/2), 4.4BSD-Lite, and 4.4BSD-Lite2 sources. NetBSD runs on fifty four different system architectures (ports), featuring seventeen machine architectures across fifteen distinct CPU families, and is being ported to more. The NetBSD 4.0_RC2 release contains complete binary releases for many different system architectures. (A few ports are not fully supported at this time and are thus not part of the binary distribution. For information on them, please see the NetBSD web site at .: **http://www.NetBSD.org/**)

NetBSD is a completely integrated system. In addition to its highly portable, high performance kernel, NetBSD features a complete set of user utilities, compilers for several languages, the X Window System, firewall software and numerous other tools, all accompanied by full source code.

NetBSD is a creation of the members of the Internet community. Without the unique cooperation and coordination the net makes possible, it's likely that NetBSD wouldn't exist.

Changes Between The NetBSD 3.0 and 4.0 Releases

The NetBSD 4.0 release provides numerous significant functional enhancements, including support for many new devices, integration of hundreds of bug fixes, new and updated kernel subsystems, and many user-land enhancements. The result of these improvements is a stable operating system fit for production use that rivals most commercially available systems.

It is impossible to completely summarize more than a year of development that went into the NetBSD 4.0_RC2 release.

The complete list of changes can be found in the CHANGES:

ftp://ftp.NetBSD.org/pub/NetBSD/NetBSD-4.0/CHANGES

and CHANGES-4.0:

ftp://ftp.NetBSD.org/pub/NetBSD/NetBSD-4.0/CHANGES-4.0

files in the top level directory of the NetBSD 4.0 release tree. Some highlights include:

Networking

- `agr`(4): new pseudo-device driver for link level aggregation.
- IPv6 support was extended with an RFC 3542-compliant API and added for `gre`(4) tunnels and the `tun`(4) device.
- A NDIS-wrapper was added to use Windows binary drivers on the i386 platform, see `ndiscvt`(8).
- The IPv4 source-address selection policy can be set from a number of algorithms. See "IPSRCSEL" in `options`(4) and `in_getifa`(9).
- Imported `wpa_supplicant`(8) and `wpa_cli`(8). Utilities to connect and handle aspects of 802.11 WPA networks.

- Imported `hostapd`(8). An authenticator for IEEE 802.11 networks.
- `carp`(4): imported Common Address Redundancy Protocol to allow multiple hosts to share a set of IP addresses for high availability / redundancy, from OpenBSD.
- ALTQ support for the PF packet filter.
- `ftpd`(8) can now run in standalone mode, instead of from `inetd`(8).
- `tftp`(1) now has support for multicast TFTP operation in open-loop mode, server is in progress.

Filesystems

- `scan_ffs`(8), `scan_lfs`(8): Utilities to find FFSv1/v2 and LFS partitions to recover lost disklabels.
- tmpfs: Added a new memory-based file system aimed at replacing mfs. Contrary to mfs, it is not based on a disk file system, so it is more efficient both in overall memory consumption and speed. See `mount_tmpfs`(8).
- Added UDF support for optical media and block devices, see `mount_udf`(8). Read-only for now.
- NFS export list handling was changed to be filesystem independent.
- LFS: Lots of stability improvements and new cleaner daemon. It is now also possible to use LFS as root filesystem.
- Support for System V Boot File System was added, see `newfs_sysvbfs`(8) and `mount_sysvbfs`(8).

Drivers

- Audio:
  - Support for new models on drivers such as Intel ICH8/6300ESB, NVIDIA nForce 3/4, etc.
  - Added support for AC'97 modems.
  - `auich`(4): added support to handle the AC'97 modem as audio device, enabled with the kernel option "AUICH_ATTACH_MODEM"
  - `azalia`(4): added support for S/PDIF.
- Hardware Monitors:
  - `amdpm`(4): added support for the i2c bus on the AMD-8111 used on many Opteron motherboards and for the Analog Devices ADT7464 hardware monitor chip.
  - `adt7467c`(4): new driver for Analog Devices ADT7467 and ADM1030 hardware monitor chips.
  - `ipmi`(4): new driver for motherboards implementing the Intelligent Platform Management Interface 1.5 or 2.0, from OpenBSD.
  - `it`(4): new driver for iTE 8705F/8712F and SiS 950 hardware monitors.
  - The `lm`(4) driver was rewritten and support for more chips was added, for example for Winbond W83627HF, W83627THF, W83627DHG and Asus AS99127F.
  - `owtemp`(4): new driver for the 1-Wire temperature sensors.
  - `tmp121temp`(4): new driver for the Texas Instruments TMP121 temperature sensor.
  - `ug`(4): new driver for ASUS Abit uGuru hardware monitor found on newer ASUS motherboards.

- Networking:
  - ath(4): updated HALs with support for WiSOC (AR531x) and 32bit SPARC.
  - bge(4): added support for the following chips: BCM5753, BCM5753M, BCM5715, BCM5754, BCM5755 and BCM5787. Numerous improvements and bugfixes were made too.
  - kse(4): new driver for Micrel KSZ8842/8841 PCI network cards.
  - msk(4): new driver for Marvell Yukon 2 GigE PCI network cards, from OpenBSD.
  - nfe(4): new driver for NVIDIA nForce Ethernet network cards, from OpenBSD.
  - ral(4): new 802.11 driver for PCI/Cardbus Ralink RT2500, RT2501, RT2600, RT2661 and RT2500 USB chipsets, from OpenBSD.
  - rum(4): new 802.11 driver for USB Ralink RT2501 and RT2601 chipsets, from OpenBSD.
  - sip(4): now works on sparc64.
  - tlp(4): added support for ASIX AX88140A and AX88141.
  - vr(4): added support for the VIA Rhine III.
  - wm(4): added support for i8003, ICH8, ICH9 and others.
  - wpi(4): new driver for Intel PRO/Wireless 3945ABG PCI 802.11 network cards, from OpenBSD.
- Security:
  - glxsb(4): new driver for the AMD Geode LX AES Security Block that provides random numbers and AES acceleration, from OpenBSD.
- Power Management:
  - Support for Intel Speedstep SMI on PIIX4 PCI-ISA for i386.
  - Support for AMD PowerNow and Cool'n'Quiet Technology on K7 and K8 CPUs (both in 32 and 64 bit mode), including Athlon Mobile, Athlon64, Opteron or X2.
  - Support for more Enhanced Speedstep CPUs, including VIA C7/Eden and Intel Core Solo/Duo/Duo2.
- Storage:
  - ahcisata(4): new driver for AHCI 1.0 and 1.1 compliant SATA controllers.
  - ataraid(4): added support to handle Adaptec HostRAID and VIA V-Tech software RAID.
  - ciss(4): new driver for HP/Compaq 5th+ generation Smart ARRAY controllers, from OpenBSD.
  - fdc(4): added support for SBus based sparc64 machines and fixed formatting on sparc.
  - gcscide(4): new driver for the AMD Geode CS5535 Companion Device IDE controller.
  - jmide(4): new driver for JMicron Technology JMB36x PCIe to SATA II/PATA controllers.
  - mfi(4): new driver for LSI Logic and Dell MegaRAID SAS controllers, from OpenBSD.
  - njata(4): new driver for Workbit NinjaATA-32 CardBus IDE controller.
  - svwsata(4): new driver for Serverworks K2 SATA controllers, from OpenBSD.
  - viaide(4) added support for the VIA VT8237A SATA controller and AMD CS5536 Companion Device IDE Controller.

- USB:
  - ucycom(4): new driver for Cypress microcontroller based serial devices.
  - uipaq(4): new driver for the iPAQ devices.
  - uslsa(4): new driver for Silicon Labs CP210x series serial adapters.
  - utoppy(4): new driver for the Topfield TF5000PVR range of digital video recorders.

Platforms

- i386:
  - Added support for the for Multiboot specification. This means much improved support for loading the kernel by GRUB, including passing in parameters to the kernel.
  - vesafb(4): added new framebuffer driver that supports VESA BIOS (VBE) 2.0 extensions and up.
  - Added cd9660 file system support to the BIOS bootloader.
- evbarm: New platform support for Arcom Viper PXA255-based single board, Atmark Techno Armadillo-9 and Armadillo-210, Linksys NSLU2 (a.k.a. "Slug") and I-O DATA HDL-G Giga LANDISK NAS devices.
- evbmips: Add support for Alchemy Au1550 processors, DBAu1550 boards, Alchemy Au15XX PCI host, (OMS-AL400/128) and Atheros AR5312 SoC.
- New port ews4800mips: NEC's MIPS based EWS4800 workstations.
- cobalt: Add support from booting off raidframe RAID1 mirrors.
- hpcmips: Added the teliosio(4) driver for the Sharp Telios LCD screen and Battery unit.
- New port landisk: port to the SH4 processor based NAS appliances, supporting models by I-O DATA (USL-5P, HDL-U, HDL-AV, HDL-W and HDLM-U series, SuperTank LAN Tank, UHDL-160U and UHDL-300U) and Plextor PX-EH16L, PX-EH25L and PX-EH40L.
- prep: This port has been modernized, and support for five additional machines has been added, among them the IBM 7024-E20 and 7025-F30 models and Motorola Powerstack E1. Additionally, sysinst support was added, and the bootloader process was improved, allowing easy installation and upgrade to future releases.
- Xen: support for Xen3 domU and dom0, including support for hardware virtualization on CPUs that support it.

Kernel subsystems

- Improved Firewire (IEEE1394) support imported from FreeBSD.
- The midi(4) framework got a complete overhaul for better support of Active Sensing and improved handling of tempo and timebase changes.
- Added a Bluetooth protocol stack including:
  - hardware drivers: ubt(4) for USB controllers, and bt3c(4) for the 3Com Bluetooth PC-Card.
  - socket based access to the HCI, L2CAP, RFCOMM and SCO protocols.
  - pseudo drivers for integrating services on remote Bluetooth devices such as Keyboards, Mice and SCO Audio into the NetBSD device framework.

  See bluetooth(4), bthset(1) and btpin(1).

- Imported the bio(4) framework from OpenBSD, to query/control block device controllers. Currently supporting the mfi(4) driver.
- Kernel uses stateful read-ahead algorithm.
- dkctl(8) can be used to switch buffer queuing strategies on the fly, see also bufq(9).
- fileassoc(9) is used by Veriexec, it adds in-kernel and file-system independent file meta-data association interface.
- firmload(9): An API for loading firmware images used by various hardware devices.
- gpio(4): Imported General Purpose I/O framework from OpenBSD.
- onewire(4): Imported Dallas Semiconductor 1-wire bus framework from OpenBSD.
- The proplib(3) protocol was added for sending property lists to/from the kernel using ioctls.
- spi(4): New SPI (Serial Peripherial Interface) framework.
- timecounter(9) adds a new time-keeping infrastructure along with NTP API 4 nanokernel implementation. Almost all platforms were changed to support this API.
- Start of 32bit-Linux-emulation for amd64 (COMPAT_LINUX32).
- wscons(4) console driver supports splash screens, scrolling, progress bar for kernel and boot messages.

Kernel interfaces have continued to be refined, and more subsystems and device drivers are shared among the different ports. You can look for this trend to continue.

Security

- The FAST_IPSEC IPsec implementation was extended to use hardware acceleration for IPv6, in addition to the hardware accelerated IPv4 that was available before. See fast_ipsec(4) for more information.
- mprotect(2) got restrictions to enforce W^X policies, from PaX. See options(4), sysctl(3), and paxctl(1).
- GCC 4's support for stack smashing protection (SSP) was enabled by adding libssp, see security(8).
- The kernel authorization framework kauth(9) was added, replacing the traditional BSD credential management and privileged operation access control with an abstract layer, allowing the implementation of various security models either as part of the NetBSD distribution or as third-party LKMs.

  NetBSD's kernel authorization is a hybrid clean-room implementation of a similar interface developed by Apple, extending its capabilities and combining concepts of credential inheritance control.

Userland

- 3rd party software updates:
  - BIND 9.4.1-P1
  - OpenSSL 0.9.8d
  - CVS 1.11.21
  - OpenSSH 4.4
  - gettext 0.14.4
  - PF from OpenBSD 3.7

  - (n)awk 20050424
  - Postfix 2.4.5
  - am-utils 6.1.3
  - file 4.21
  - zlib 1.2.3
  - GNU binutils 2.16.1
  - GNU groff 1.19.2
  - IPFilter 4.1.23
  - GNU gcc 4.1.1
  - NTP 4.2.2p2
  - pppd 2.4.4
- `cksum`(1) can now verify checksums.
- `identd`(1): added support for forwarding ident queries and receiving of proxied ident queries.
- `getent`(1): added support for the ethers database.
- iSCSI target (server) code added, see `iscsi-target`(8); Initiator (client) code is underway.
- `lockstat`(8): new command to display a summary of kernel locking events recorded over the lifetime of a called program.
- Various utilities to support Bluetooth were added:
  - `btconfig`(8) for controller configuration.
  - `btdevctl`(8) to manage pseudo devices relating to remote services.
  - `bthcid`(8) and `btpin`(1) for authenticating radio connections.
  - `sdpd`(8) for providing service discovery to remote devices.
  - `sdpquery`(1) for querying services on remote devices.
  - `rfcomm_sppd`(1) to access remote services over RFCOMM via stdio or pty.
  - `bthset`(1) for making connections to Bluetooth headsets.

Besides this list, there there have also been innumerable bug fixes and other miscellaneous enhancements of course.

Components removed from NetBSD

In this release of NetBSD, some software components known from previous releases were removed from the system. In some cases those were components that are not useful anymore or their utility does not justify maintenance overhead. Other components were not working properly and there was lack of interest in fixing them.

- Sushi ...
- Vinum ...
- Sendmail was removed. Postfix is the MTA and provides the `sendmail`(1) command line tool. Postfix has been included with NetBSD since NetBSD 1.5 was released in December 2005. Details about Postfix can be found in the NetBSD Guide:

http://www.NetBSD.org/docs/guide/en/chap-mail.html.
For those who need Sendmail, it is available from pkgsrc in the `mail/sendmail` and `mail/sendmail813` packages.

- NETCCITT ...
- NETNS ...
- UUCP was removed. The NetBSD improvements were merged into the pkgsrc version. For those who use UUCP tools, they are available from pkgsrc in the `net/uucp` package. The `cu`(1) command is available as a frontend to `tip`(1).
- The Fortran 77 compiler (g77) has been removed with the transition from GCC 3 to GCC 4, which does not include it. For those who need it, it is available from pkgsrc in the `lang/gcc3-f77` package.
- The evbsh5 port has been removed from NetBSD due to lack of interest, compounded by a lack of available SH5 hardware.

The Future of NetBSD

The NetBSD Foundation has been incorporated as a non-profit organization. Its purpose is to encourage, foster and promote the free exchange of computer software, namely the NetBSD Operating System. The foundation will allow for many things to be handled more smoothly than could be done with our previous informal organization. In particular, it provides the framework to deal with other parties that wish to become involved in the NetBSD Project.

The NetBSD Foundation will help improve the quality of NetBSD by:

- providing better organization to keep track of development efforts, including co-ordination with groups working in related fields.
- providing a framework to receive donations of goods and services and to own the resources necessary to run the NetBSD Project.
- providing a better position from which to undertake promotional activities.
- periodically organizing workshops for developers and other interested people to discuss ongoing work.

We intend to begin narrowing the time delay between releases. Our ambition is to provide a full release every six to eight months.

We hope to support even *more* hardware in the future, and we have a rather large number of other ideas about what can be done to improve NetBSD.

We intend to continue our current practice of making the NetBSD-current development source available on a daily basis.

We intend to integrate free, positive changes from whatever sources submit them, providing that they are well thought-out and increase the usability of the system.

Above all, we hope to create a stable and accessible system, and to be responsive to the needs and desires of NetBSD users, because it is for and because of them that NetBSD exists.

Sources of NetBSD

Refer to .: **http://www.NetBSD.org/mirrors/**

NetBSD 4.0_RC2 Release Contents

The root directory of the NetBSD 4.0_RC2 release is organized as follows:

`.../NetBSD-4.0_RC2/`

`CHANGES`	Changes since earlier NetBSD releases.
`LAST_MINUTE`	Last minute changes.
`MIRRORS`	A list of sites that mirror the NetBSD 4.0_RC2 distribution.
`README.files`	README describing the distribution's contents.
`TODO`	NetBSD's todo list (also somewhat incomplete and out of date).
`patches/`	Post-release source code patches.
`source/`	Source distribution sets; see below.

In addition to the files and directories listed above, there is one directory per architecture, for each of the architectures for which NetBSD 4.0_RC2 has a binary distribution.

The source distribution sets can be found in subdirectories of the `source` subdirectory of the distribution tree. They contain the complete sources to the system. The source distribution sets are as follows:

gnusrc This set contains the "gnu" sources, including the source for the compiler, assembler, groff, and the other GNU utilities in the binary distribution sets.
79 MB gzipped, 367 MB uncompressed

pkgsrc This set contains the "pkgsrc" sources, which contain the infrastructure to build third-party packages.
24 MB gzipped, 200 MB uncompressed

sharesrc This set contains the "share" sources, which include the sources for the man pages not associated with any particular program; the sources for the typesettable document set; the dictionaries; and more.
5 MB gzipped, 20 MB uncompressed

src This set contains all of the base NetBSD 4.0_RC2 sources which are not in **gnusrc**, **sharesrc**, or **syssrc**.
37 MB gzipped, 176 MB uncompressed

syssrc This set contains the sources to the NetBSD 4.0_RC2 kernel for all architectures; `config`(1); and `dbsym`(8).
26 MB gzipped, 140 MB uncompressed

xsrc This set contains the sources to the X Window System.
84 MB gzipped, 450 MB uncompressed

All the above source sets are located in the `source/sets` subdirectory of the distribution tree.

The source sets are distributed as compressed tar files. Except for the **pkgsrc** set, which is traditionally unpacked into `/usr/pkgsrc`, all sets may be unpacked into `/usr/src` with the command:

```
# cd / ; tar -zxpf set_name.tgz
```

In each of the source distribution set directories, there are files which contain the checksums of the files in the directory:

`BSDSUM` Historic BSD checksums for the various files in that directory, in the format produced by the command:
cksum -o 1 *file*.

`CKSUM` POSIX checksums for the various files in that directory, in the format produced by the command:
cksum *file*.

`MD5` MD5 digests for the various files in that directory, in the format produced by the command:
cksum -m *file*.

`SYSVSUM` Historic ATT System V UNIX checksums for the various files in that directory, in the format produced by the command:
cksum -o 2 *file*.

The MD5 digest is the safest checksum, followed by the POSIX checksum. The other two checksums are provided only to ensure that the widest possible range of system can check the integrity of the release files.

NetBSD/amiga subdirectory structure

The amiga-specific portion of the NetBSD 4.0_RC2 release is found in the `amiga` subdirectory of the distribution: `.../NetBSD-4.0_RC2/amiga/`. It contains the following files and directories:

`INSTALL.html`
`INSTALL.ps`
`INSTALL.txt`
`INSTALL.more` Installation notes in various file formats, including this file. The `.more` file contains underlined text using the `more`(1) conventions for indicating italic and bold display.
`binary/`
`kernel/`
`netbsd-GENERIC.gz`
A gzipped NetBSD kernel containing code for everything supported in this release.
`sets/` amiga binary distribution sets; see below.
`installation/`
`floppy/` amiga boot and installation floppies; see below.
`miniroot/`
amiga miniroot file system image; see below.
`misc/` Miscellaneous amiga installation utilities; see installation section, below.

Miniroot file system

The Amiga now uses a single miniroot file system for both an initial installation and for an upgrade. A gzipped version is available, for easier downloading. (The gzipped version has the **.gz** extension added to their names.)

`miniroot.fs` This file contains a BSD root file system setup to help you install the rest of NetBSD or to upgrade a previous version of NetBSD. This includes formatting and mounting your `/` (root) and `/usr` partitions and getting ready to extract (and possibly first fetching) the distribution sets. There is enough on this file system to allow you to make a SLIP or PPP connection, configure an Ethernet, mount an NFS file system or ftp. You can also load distribution sets from a SCSI tape or from one of your existing AmigaDOS partitions.

Binary distribution sets

The NetBSD amiga binary distribution sets contain the binaries which comprise the NetBSD 4.0_RC2 release for the amiga. The binary distribution sets can be found in the `amiga/binary/sets` subdirectory of the NetBSD 4.0_RC2 distribution tree, and are as follows:

base The NetBSD 4.0_RC2 amiga **base** binary distribution. You *must* install this distribution set. It contains the base NetBSD utilities that are necessary for the system to run and be minimally functional. It includes shared library support, and excludes everything described below.
16 MB gzipped, 46 MB uncompressed

comp Things needed for compiling programs. This set includes the system include files (`/usr/include`) and the various system libraries (except the shared libraries, which are included as part of the **base** set). This set also includes the manual pages for all of the utilities it contains, as well as the system call and library manual pages.
18 MB gzipped, 69 MB uncompressed

etc This distribution set contains the system configuration files that reside in `/etc` and in several other places. This set *must* be installed if you are installing the system from scratch, but should *not* be used if you are upgrading.
1 MB gzipped, 1 MB uncompressed

games This set includes the games and their manual pages.
3 MB gzipped, 7 MB uncompressed

kern-GENERIC
This set contains a NetBSD/amiga 4.0_RC2 `GENERIC` kernel, named `/netbsd`. You *must* install this distribution set.
2 MB gzipped, 4 MB uncompressed

man This set includes all of the manual pages for the binaries and other software contained in the **base** set. Note that it does not include any of the manual pages that are included in the other sets.
8 MB gzipped, 30 MB uncompressed

misc This set includes the (rather large) system dictionaries, the typesettable document set, and other files from `/usr/share`.
3 MB gzipped, 9 MB uncompressed

text This set includes NetBSD's text processing tools, including `groff`(1), all related programs, and their manual pages.
2 MB gzipped, 7 MB uncompressed

NetBSD maintains its own set of sources for the X Window System in order to assure tight integration and compatibility. These sources are based on XFree86, and tightly track XFree86 releases. They are currently equivalent to XFree86 4.4.0. Binary sets for the X Window System are distributed with NetBSD. The sets are:

xbase The basic files needed for a complete X client environment. This does not include the X servers.
6 MB gzipped, 17 MB uncompressed

xcomp The extra libraries and include files needed to compile X source code.
10 MB gzipped, 37 MB uncompressed

xfont Fonts needed by the X server and by X clients.
31 MB gzipped, 39 MB uncompressed

xetc Configuration files for X which could be locally modified.
0.03 MB gzipped, 0.17 MB uncompressed

xserver The X server.
4 MB gzipped, 9 MB uncompressed

The amiga binary distribution sets are distributed as gzipped tar files named with the extension **.tgz**, e.g. `base.tgz`.

The instructions given for extracting the source sets work equally well for the binary sets, but it is worth noting that if you use that method, the filenames stored in the sets are relative and therefore the files are extracted *below the current directory*. Therefore, if you want to extract the binaries into your system, i.e. replace the system binaries with them, you have to run the **`tar -xpf`** command from the root directory (`/`) of your system. This utility is used only in a Traditional method installation.

Note: Each directory in the amiga binary distribution also has its own checksum files, just as the source distribution does.

NetBSD/amiga System Requirements and Supported Devices

NetBSD 4.0_RC2 runs on any Amiga that has a 68020 or better CPU with some form of MMU, and on 68060 DraCos.

NetBSD does not, and will never, run on run on A1000, A500, A600, A1200, A2000, A4000/EC030, CDTV and CD32 systems that are not enhanced by a CPU board.

For 68020 and 68030 systems, a FPU is recommended but not required for the system utilities. 68LC040, 68040V and 68LC060 systems don't work correctly at the moment.

The minimal configuration requires 6 MB of RAM (not including CHIPMEM!) and about 75 MB of disk space. To install the entire system requires much more disk space, and to run X or compile the system, more RAM is recommended. (6 MB of RAM will actually allow you to compile, however it won't be speedy. X really isn't usable on a 6 MB system.)

Here is a table of recommended HD partition sizes for a full install:

Partition	Suggested	+ X	Needed	+ X
/ (root)	25 MB	25 MB	20 MB	20 MB
/usr	245 MB	270 MB	120 MB	145 MB
/var	20 MB	20 MB	5 MB	5 MB
swap	*2*RAM below 32 MB, then up to you*			

Anything else is up to you!

As you may note the recommended size of `/usr` is 125 MB greater than needed. This is to leave room for a kernel source and compile tree as you will probably want to compile your own kernel. `GENERIC` is large and bulky to accommodate all people. For example, most people's machines have an FPU, so you do not need the bulky FPU_EMULATE option.

Preconfigured or precompiled packages are installed below `/usr/pkg` by default. You should either make `/usr` larger (if you intend to install a lot of them), make `/usr/pkg` an additional partition, use the **`-p`** option to **`pkg_add`** to install them in a different place, or link `/usr/pkg` to a different place.

If you only have less than 8 MB of fast memory, you should make your swap partition larger, as your system will be doing much more swapping. Especially: do *not* place it onto a old small (and normally slow) disk!

Supported devices

- A4000/A1200 IDE controller, including ATAPI devices
- SCSI host adapters
  - 33c93 based boards: A2091, A3000 builtin, A3000 builtin modified for Apollo accelerator board (please note that this is not the same as the SCSI host adapter on the Apollo accelerator board itself, which is unsupported), and GVP series II.
  - 53c80 based boards: 12 Gauge, IVS, Wordsync/Bytesync and Emplant The Emplant SCSI adapter has been reported by a party to hang after doing part of the installation without problems
  - 53c710 based boards: A4091, Magnum, Warp Engine, Zeus and DraCo builtin
  - FAS216 based SCSI boards: FastLane Z3, Blizzard I and II, Blizzard IV, Blizzard 2060, CyberSCSI Mk I and II
  - 53c770 based SCSI boards: Cyberstorm Mk III SCSI, Cyberstorm PPC SCSI
- Video controllers
  - ECS, AGA and A2024 built in on various Amigas
  - Retina Z2 (no X server available), Retina Z3 and Altais
  - Cirrus CL GD 54xx based boards: GVP Spectrum, Picasso II, II+ and IV, Piccolo and Piccolo SD64
  - Tseng ET4000 based boards: Domino and Domino16M proto, oMniBus, Merlin
  - A2410 (no X server available)
  - Cybervision 64
  - Cybervision 64/3D
- Audio I/O
  - Amiga builtin
  - Melody Mpeg-audio layer 2 board
  - Repulse audio board
- Ethernet controllers
  - A2065 Ethernet
  - Hydra Ethernet
  - ASDG Ethernet
  - A4066 Ethernet
  - Ariadne Ethernet
  - Ariadne II Ethernet
  - Quicknet Ethernet
  - X-surf Ethernet port
- ARCnet controllers
  - A2060 ARCnet
- Most SCSI tape drives, including Archive Viper, Cipher SCSI-2 ST150
- SCSI-2 scanners behaving as SCSI-2 scanner devices, HP Scanjet II, Mustek SCSI scanner. SCSI scanner support is machine independent, so it should work, but hasn't been tested yet on most Amiga configurations. There are reports that the Mustek and HP ScanJet hang if accessed from the A3000. This might apply to other 33C93-Adapters, too.
- Most SCSI CD-ROM drives
- Serial/Parallel cards

  - HyperCom 3Z, HyperCom 4, HyperCom 3+ and 4+
  - MultiFaceCard II and III
  - A2232 (normal and clockdoubled)
  - IOBlix Zorro-Bus
- Amiga floppy drives with Amiga (880/1760kB) and IBM (720/1440kB) encoding. Our floppy driver doesn't notice when mounted floppies are write-protected at the moment. Your floppy will stay unchanged, but you might not notice that you didn't write anything due to the buffer cache. Also note that HD floppy drives only get detected as such if a HD floppy is inserted at boot time.
- Amiga parallel port
- Amiga serial port
- Amiga mouse
- DraCo serial port, including serial mouse
- DraCo parallel printer port
- Real-time clocks
  - A2000, A3000, A4000 builtin (r/w)
  - DraCo builtin (r/o)

If its not on the above lists, there is no support for it in this release. Especially (but this is an incomplete list), there are no drivers for: Blizzard III SCSI option, Ferret SCSI, Oktagon SCSI.

Getting the NetBSD System on to Useful Media

Note that if you are installing or upgrading from a writable media, the media can be write-protected if you wish. These systems mount a root image from inside the kernel, and will not need to write to the media. If you booted from a floppy, the floppy disk may be removed from the drive after the system has booted.

Installation is supported from several media types, including:

- AmigaDOS
- CD-ROM / DVD
- MS-DOS floppy
- FTP
- Remote NFS partition
- Tape
- Existing NetBSD partitions, if performing an upgrade

The steps necessary to prepare the distribution sets for installation depend upon which installation medium you choose. The steps for the various media are outlined below.

AmigaDOS partition

To install NetBSD from an AmigaDOS partition, you need to get the NetBSD distribution sets you wish to install on your system on to an AmigaDOS partition.

Note where you place the files as you will need this later.

Once you have done this, you can proceed to the next step in the installation process, preparing your hard disk.

CD-ROM / DVD To install NetBSD from a CD-ROM drive, make sure it is a SCSI CD-ROM on a SCSI bus currently supported by NetBSD (refer to the supported hardware list) or an ATAPI CD-ROM connected to the A1200 or A4000 internal IDE connector. If it is a SCSI CD-ROM on a non-supported SCSI bus like Blizzard-3 SCSI or Apollo SCSI you must first copy the distribution sets to an AmigaDOS partition as described above.

If your SCSI CD-ROM is connected to a supported SCSI host adapter, or it is an ATAPI cd-rom connected to the A1200/A4000 internal IDE connector, simply put the CD into the drive before installation.

Find out where the distribution set files are on the CD-ROM or DVD. Likely locations are `binary/sets` and `amiga/binary/sets`.

Proceed to the instruction on installation.

MS-DOS floppy

NetBSD doesn't include split sets to keep the distribution size down. They can be created on a separate machine using the `split`(1) command, running e.g. **`split -b 235k base.tgz base.`** to split the `base.tgz` file from `amiga/binary/sets` into files named `base.aa`, `base.ab`, and so on. Repeat this for all `set_name.tgz` files, splitting them into `set_name.`*`xx`* files. Count the number of `set_name.`*`xx`* files that make up the distribution sets you want to install or upgrade. You will need one sixth that number of 1.44 MB floppies.

Format all of the floppies with MS-DOS. Do *not* make any of them bootable MS-DOS floppies, i.e. don't use `format /s` to format them. (If the floppies are bootable, then the MS-DOS system files that make them bootable will take up some space, and you won't be able to fit the distribution set parts on the disks.) If you're using floppies that are formatted for MS-DOS by their manufacturers, they probably aren't bootable, and you can use them out of the box.

Place all of the `set_name.`*`xx`* files on the MS-DOS disks.

Once you have the files on MS-DOS disks, you can proceed to the next step in the installation or upgrade process. If you're installing NetBSD from scratch, go to the section on preparing your hard disk, below. If you're upgrading an existing installation, go directly to the section on upgrading.

FTP

The preparations for this installation/upgrade method are easy; all you need to do is make sure that there's an FTP site from which you can retrieve the NetBSD distribution when you're about to install or upgrade. If you don't have DHCP available on your network, you will need to know the numeric IP address of that site, and, if it's not on a network directly connected to the machine on which you're installing or upgrading NetBSD, you need to know the numeric IP address of the router closest to the NetBSD machine. Finally, you need to know the numeric IP address of the NetBSD machine itself. If you don't have access to a functioning nameserver during installation, the IPv4 address of **ftp.NetBSD.org** is `204.152.184.36` and the IPv6 address is `2001:4f8:1:c:230:48ff:fe31:43f2` (as of December, 2006).

Once you have this information, you can proceed to the next step in the installation or upgrade process. If you're installing NetBSD from scratch, go to the section on preparing your hard disk, below. If you're upgrading an existing installation, go directly to the section on upgrading.

Note: This method of installation is recommended for those familiar with using BSD network configuration and management commands. If you aren't, this documentation should help, but is not intended to be all-encompassing.

NFS

Place the NetBSD distribution sets you wish to install into a directory on an NFS server, and make that directory mountable by the machine on which you are installing or upgrading NetBSD. This will probably require modifying the `/etc/exports` file on of the NFS server and resetting its mount daemon (mountd). (Both of these actions will probably require superuser privileges on the server.)

You need to know the numeric IP address of the NFS server, and, if you don't have DHCP available on your network and the server is not on a network directly connected to the machine on which you're installing or upgrading NetBSD, you need to know the numeric IP address of the router closest to the NetBSD machine. Finally, you need to know the numeric IP address of the NetBSD machine itself.

Once the NFS server is set up properly and you have the information mentioned above, you can proceed to the next step in the installation or upgrade process. If you're installing NetBSD from scratch, go to the section on preparing your hard disk, below. If you're upgrading an existing installation, go directly to the section on upgrading.

Note: This method of installation is recommended for those already familiar with using BSD network configuration and management commands. If you aren't, this documentation should help, but is not intended to be all-encompassing.

Tape To install NetBSD from a tape, you need to make a tape that contains the distribution set files, in 'tar' format.

If you're making the tape on a UNIX-like system, the easiest way to do so is probably something like:

```
# tar -cf tape_device dist_directories
```

where *tape_device* is the name of the tape device that describes the tape drive you're using; possibly `/dev/rst0`, or something similar, but it will vary from system to system. (If you can't figure it out, ask your system administrator.) In the above example, *dist_directories* are the distribution sets' directories, for the distribution sets you wish to place on the tape. For instance, to put the **misc, base,** and **etc** distributions on tape (in order to do the absolute minimum installation to a new disk), you would do the following:

```
# cd .../NetBSD-4.0_RC2
# cd amiga/binary
# tar -cf tape_device misc etc kern
```

Note: You still need to fill in *tape_device* in the example.

Once you have the files on the tape, you can proceed to the next step in the installation or upgrade process. If you're installing NetBSD from scratch, go to the section on preparing your hard disk, below. If you're upgrading an existing installation, go directly to the section on upgrading.

Preparing your System for NetBSD installation

You will need an AmigaDOS hard drive prep tool to prepare your hard drives for use with NetBSD/amiga. HDToolBox is provided with the system software and on floppy installation disks since Release 2.0 of AmigaDOS, so we will provide instructions for its use.

Note that NetBSD can't currently be installed on disks with a sector size other than 512 bytes (e.g., "640 MB" 90mm M-O media). You can, however, mount ADOSFS partitions on such M-O's.

Preparing your hard disk with HDToolBox

A full explanation of HDToolBox can be found with your AmigaDOS manuals and is beyond the scope of this document.

The first time you partition a drive, you need to set its drive type so that you have working geometry parameters. To do this you enter the "Change drive type" menu, and either use "read parameters from drive" or set them manually.

Note you will be modifying your HD's. If you mess something up here you could lose everything on all the drives that you configure. It is therefore advised that you:

1. Write down your current configurations. Do this by examining each partition on the drive and the drives parameters (from Change drive type.)
2. Back up the partitions you are keeping.

What you need to do is partition your drives; creating at least root, swap and `/usr` partitions and possibly at least one more for `/usr/local` if you have the space.

This should be done as the HDToolBox manual describes. One thing to note is that if you are not using a Commodore controller you will need to specify the device your SCSI controller uses, e.g. if you have a Warp Engine you would:

From cli

`hdtoolbox warpdrive.device`

From wb Set the tooltype

`SCSI_DEVICE_NAME=warpdrive.device`

The important things you need to do above and beyond normal partitioning includes (from Partition Drive section):

1. Marking all NetBSD partitions as non-bootable, with two exceptions: the root partition (/), if you want to boot NetBSD directly, or the swap partition, if you want to boot the installation miniroot directly.
2. Changing the file system parameters of the partitions to NetBSD ones. This must be done from the partitioning section and "Advanced options" must be enabled.

To make the needed changes:

1. Click the "Adv. Options" button
2. Click the "Change file system" button
3. Choose "Custom File System"
4. Turn off "Automount" if on.
5. Set the dostype to one of these three choices:

```
root partition  : 0x4e425207  (NBR\007)
swap partition  : 0x4e425301  (NBS\001)
other partitions: 0x4e425507  (NBU\007)
```

   Here '`other`' refers to other partitions you will format for reading and writing under NetBSD (e.g. `/usr`)

   Make sure you press `RETURN` to enter this value as some versions of HDToolBox will forget your entry if you don't.
6. Turn custom boot code off
7. Set Reserved Blocks start and end to 0.
8. Click Ok.

On the root (/) (and, for installation, swap) partition, set instead this:

1. Turn custom boot code on
2. Set Reserved Blocks start and end to 0.
3. Set Number of Custom Boot Blocks to 16.
4. Set Automount This Partition on

5. Click Ok.

   Mask and maxtransfer are not used with NetBSD.

Caveat: The swap (for installation) and the root partition (if you plan to use the bootblocks) *must be within the first* 4 gigabytes of the disk! The reason for the former is that xstreamtodev uses trackdisk.device compatible I/O-calls, the reason for the latter is that the bootblock gets a 32bit partition offset from the operating system.

Once this is done NetBSD/amiga will be able to recognize your disks and which partitions it should use.

Transferring the miniroot file system

The NetBSD/amiga installation or upgrade now uses a *miniroot* file system which is installed on the partition used by NetBSD for swapping. This removes the requirement of using a floppy disk for the file system used by the installation or upgrade process. It also allows more utilities to be present on the file system than would be available when using an 880 KB floppy disk.

Once the hard disk has been prepared for NetBSD, the miniroot file system (`miniroot.fs`) is transferred to the swap partition configured during the hard disk prep (or the existing swap partition in the case of an upgrade). The xstreamtodev utility provided in the `amiga/installation/misc` directory can be used on AmigaDOS to transfer the file system for either a new installation or an upgrade. The file system can also be transferred on an existing NetBSD system for an update by using dd. This should only be done after booting NetBSD into single-user state. It may also be possible to shutdown to single-user, providing that the single-user state processes are not using the swap partition.

On AmigaDOS, the command:

xstreamtodev --input=miniroot.fs --rdb-name=swap partition

where swap partition is the name you gave to the NetBSD partition to be used for swapping. If **xstreamtodev** is unable to determine the SCSI driver device name or the unit number of the specified partition, you may also need to include the option

--device=driver.name

and/or

--unit=SCSI unit number

To transfer the miniroot using NetBSD, you should be booted up in single user state on the current NetBSD system, or use the **shutdown now** command to shutdown to single-user state. Then copy the miniroot using **dd**:

dd if=miniroot.fs of=/dev/rsd0b

where `/dev/rsd0b` should be the device path of the swap partition your system is configured to use. Once the file is copied, reboot back to AmigaDOS to boot the upgrade kernel.

Caveat: Once you have started installation, if you abort it and want to retry you must reinstall the `miniroot.fs` on the swap partition.

Installing the NetBSD System

Installing NetBSD is a relatively complex process, but, if you have this document in hand and are careful to read and remember the information which is presented to you by the install program, it shouldn't be too much trouble.

Before you begin, you must have already prepared your hard disk as detailed in the section on preparing your system for install.

The following is a walk-through of the steps necessary to get NetBSD installed on your hard disk. If you wish to stop the installation, you may press CONTROL-C at any prompt, but if you do, you'll have to begin again from scratch.

Transfer the miniroot file system onto the hard disk partition used by NetBSD for swapping, as described in the "Preparing your System for NetBSD Installation" section above.

Booting

NetBSD, with boot blocks installed

[This description is for V40 (OS 3.1) ROMs. For older ROMs, there might be small differences. Check your AmigaDOS documentation to learn about the exact procedure.] Using bootblocks may not work on some systems, and may require a mountable file system on others.

Reboot your machine, holding down both mouse buttons if you have a 2-button mouse, the outer mouse buttons if you have a 3-button mouse. On the DraCo, press the left mouse button instead, when the boot screen prompts you for it.

From the boot menu, select **Boot Options**. Select the swap partition with the miniroot, and then **ok**. Select **Boot** now. The machine will boot the bootblock, which will prompt your for a command line. You have a few seconds time to change the default. Entering an empty line will accept the default.

The bootblock uses command lines of the form:

file [*options*]

where *file* is the kernel file name on the partition where the boot block is on, and [options] may contain the following:

If you have an AGA machine, and your monitor will handle the dblNTSC mode, you may include the **-A** option to enable the dblNTSC display mode.

If your machine has a fragmented physical memory space, as, e.g., DraCo machines, you should add the **-n2** option to enable the use of all memory segments.

Once your kernel boots

You should see the screen clear and some information about your system as the kernel configures the hardware. Note which hard disk device(s) are configured (sd0, sd1, etc.) Then you will be prompted for a root device. At this time type sd0b, where sd0 is the device which contains the swap partition you created during the hard disk preparation. When prompted for a dump device, answer '**none**' for the install (normally, you would tell it one of the swap devices). When prompted for the root file system type, confirm '**generic**', which will auto-detect it.

If the system should hang after entering the root device, try again with

netbsd -I ff -b

This disables synchronous transfer on all SCSI devices on the first bus.

The system should continue to boot. For now ignore "WARNING" messages about bad dates in clocks, and a warning about /etc/rc not existing. Eventually you will be be asked to enter the pathname of the shell, just press RETURN. After a short while, you will be asked to select the type of your keyboard. After you have entered a valid response here, the system asks you if you want to install or upgrade your system. Since you are reading the *install* section, '**i**' would be the proper response here...

The installer starts with a nice welcome messages. Read this message carefully, it also informs you of the risks involved in continuing! If you still want to go on, type '**y**'. The installer now continues by trying to figure out your disk configuration. When it is done, you will be prompted to select a root device from the list of disks it has found.

You should know at this point that the disks are *not* numbered according to their SCSI-ID! The NetBSD kernel numbers the SCSI drives (and other devices on the SCSI bus) sequentially as it finds them. The drive with the lowest SCSI-ID will be called `sd0`, the next one `sd1`, etc. Also, any ATAPI disk drives (e.g. ZIP) will be configured as "SCSI" drives, too, and will be configured before any 'real' SCSI drives if connected to the Amiga internal port on A4000/A1200 (if any are present). Real IDE drives will be configured as `wd0`, `wd1`, etc.

The installer will offer you to look at the NetBSD disk label of the disks at this point. You should do this, to find out what partition letters the NetBSD kernel assigned to the partitions you created, and as a check whether the disk number you are going to use is right.

you are now at the point of no return. If you confirm that you want to install NetBSD, your hard drive will be modified, and perhaps its contents scrambled at the whim of the install program. Type `Control-C` *now* if you don't want this.

At this time, you will need to tell the installer which partition will be associated with the different file systems. Normally, you'll want to add a partition for `/usr`, at least.

Caveat: Do not use the `rsd`*N*`c` or `sd`*N*`c` partitions for anything! They are for access to the whole disk only and do *not* correspond to any Amiga partition!

The install program will now make the file systems you specified. There should be only one error per file system in this section of the installation. It will look like this:

```
newfs: ioctl (WDINFO): Invalid argument
newfs: /dev/rsd0a: can't rewrite disk label
```

If there are any others, restart from the beginning of the installation process. This error is ok as the Amiga does not write disklabels currently. You should expect this error whenever using newfs.

The install will now ask you want to configure any network information. It ill ask for the machine's host name, domain name, and other network configuration information.

Since the network configuration might have lead to additional (nfs) file system entries, you get another chance to modify your fstab.

You are finally at the point where some real data will be put on your freshly made file systems. Select the device type you wish to install from and off you go....

Some notes:

- If you want to install from tape, please read the section about how to create such a tape.
- Some tapes (e.g. Archive Viper 150) refuse to operate with the default tape density (`nrst0`). Try `nrst0h`, `nrst0m`, or `nrst0l` instead.
- Install at least the **base** and **etc** sets.
- If you have to specify a path relative to the mount-point and you need the mount-point itself, use '`.`'.

Next you will be asked to specify the timezone. Just select the timezone you are in. The installer will make the correct setup on your root file system (`/`). After the timezone-link is installed, the installer will proceed by creating the device nodes on your root file system under `/dev`.

Be patient, this will take a while...

Next, the installer will copy your keymap settings to the new system. After this, it will copy the kernel from the installation miniroot to the newly installed / upgraded system. If the installed system already has a kernel, it will ask you for confirmation.

kern.tgz distribution set, this is an old kernel, and you should answer "y" to install a working (although restricted) INSTALL kernel.

If you did install the kern.tgz kernel, you normally should answer "n".

Finally, the installer ask you if you want to install the bootblock code on your root disk. This is a matter of personal choice and can also be done from a running NetBSD system. See the `installboot`(8) manual page about how to do this.

Once the installer is done, halt the system with the **halt** command (wait for `halted` to be displayed) and reboot. Then again boot NetBSD this time selecting the root partition (`/`) from the boot menu, and tell it to boot

```
netbsd -s
```

You need to do your final tweaks now. First mount your file systems like so:

```
mount -av
```

Your system is now complete but not completely configured; you should adjust the `/etc/sendmail.cf` file as necessary to suit your site. You should also examine and adjust the settings in `/etc/rc.conf`. You can use `vi`(1) or `ed`(1) to edit the files. If you installed the man pages you can type **man vi** or **man ed** for instructions on how to use these somewhat non-intuitive editors.

Once you are done with the rest of configuration unmount your file systems and halt your system, then reboot:

```
# cd /
# umount -av
# halt
```

Finally you can now boot your system and it will be completely functional:

```
netbsd
```

When it boots off of the hard drive, you will have a complete NetBSD system! *Congratulations!* (You really deserve them!!!)

Post installation steps

Once you've got the operating system running, there are a few things you need to do in order to bring the system into a properly configured state, with the most important ones described below.

1. Configuring `/etc/rc.conf`

   If you or the installation software haven't done any configuration of `/etc/rc.conf` (**sysinst** usually will), the system will drop you into single user mode on first reboot with the message

   ```
   /etc/rc.conf is not configured. Multiuser boot aborted.
   ```

   and with the root file system (`/`) mounted read-only. When the system asks you to choose a shell, simply press `RETURN` to get to a `/bin/sh` prompt. If you are asked for a terminal type, respond with **vt220** (or whatever is appropriate for your terminal type) and press `RETURN`. You may need to type one of the following commands to get your delete key to work properly, depending on your keyboard:

   ```
   # stty erase '^h'
   # stty erase '^?'
   ```

   At this point, you need to configure at least one file in the `/etc` directory. You will need to mount your root file system read/write with:

   ```
   # /sbin/mount -u -w /
   ```

   Change to the `/etc` directory and take a look at the `/etc/rc.conf` file. Modify it to your tastes, making sure that you set `rc_configured=YES` so that your changes will be enabled and a multi-user

boot can proceed. Default values for the various programs can be found in `/etc/defaults/rc.conf`, where some in-line documentation may be found. More complete documentation can be found in `rc.conf`(5).

If your `/usr` directory is on a separate partition and you do not know how to use **ed**, you will have to mount your `/usr` partition to gain access to **ex** or **vi**. Do the following:

```
# mount /usr
# export TERM=vt220
```

If you have `/var` on a separate partition, you need to repeat that step for it. After that, you can edit `/etc/rc.conf` with `vi`(1). When you have finished, type **exit** at the prompt to leave the single-user shell and continue with the multi-user boot.

Other values that need to be set in `/etc/rc.conf` for a networked environment are *hostname* and possibly *defaultroute*, furthermore add an *ifconfig_int* for your ⟨int⟩ network interface, along the lines of

```
ifconfig_de0="inet 123.45.67.89 netmask 255.255.255.0"
```

or, if you have *myname.my.dom* in `/etc/hosts`:

```
ifconfig_de0="inet myname.my.dom netmask 255.255.255.0"
```

To enable proper hostname resolution, you will also want to add an `/etc/resolv.conf` file or (if you are feeling a little more adventurous) run `named`(8). See `resolv.conf`(5) or `named`(8) for more information. Instead of manually configuring network and naming service, DHCP can be used by setting `dhclient=YES` in `/etc/rc.conf`.

Other files in `/etc` that may require modification or setting up include `/etc/mailer.conf`, `/etc/nsswitch.conf`, and `/etc/wscons.conf`.

2. Logging in

   After reboot, you can log in as `root` at the login prompt. Unless you've set a password in **sysinst**, there is no initial password. If you're using the machine in a networked environment, you should create an account for yourself (see below) and protect it and the "root" account with good passwords. By default, root login from the network is disabled (even via `ssh`(1)). One way to become root over the network is to log in as a different user that belongs to group "wheel" (see `group`(5)) and use `su`(1) to become root.

   Unless you have connected an unusual terminal device as the console you can just press `RETURN` when it prompts for `Terminal type? [...]`.

3. Adding accounts

   Use the `useradd`(8) command to add accounts to your system. Do not edit `/etc/passwd` directly! See `vipw`(8) and `pwd_mkdb`(8) if you want to edit the password database.

4. The X Window System

   If you have installed the X Window System, look at the files in `/usr/X11R6/lib/X11/doc` for information.

   Don't forget to add `/usr/X11R6/bin` to your path in your shell's dot file so that you have access to the X binaries.

5. Installing third party packages

   If you wish to install any of the software freely available for UNIX-like systems you are strongly advised to first check the NetBSD package system. This automatically handles any changes necessary to

make the software run on NetBSD, retrieval and installation of any other packages on which the software may depend, and simplifies installation (and deinstallation), both from source and precompiled binaries.

- More information on the package system is at
  http://www.NetBSD.org/Documentation/software/packages.html
- A list of available packages suitable for browsing is at
  ftp://ftp.NetBSD.org/pub/NetBSD/packages/pkgsrc/README.html
- Precompiled binaries can be found at ,:
  ftp://ftp.NetBSD.org/pub/NetBSD/packages/
  usually in the `4.0_RC2/amiga/All` subdir. You can install them with the following commands under `sh`(1):

  ```
  # PKG_PATH=ftp://ftp.NetBSD.org/pub/NetBSD/packages/4.0_RC2/amiga/All
  # export PKG_PATH
  # pkg_add -v tcsh
  # pkg_add -v bash
  # pkg_add -v perl
  # pkg_add -v apache
  # pkg_add -v kde
  # pkg_add -v firefox
  ...
  ```

  If you are using `csh`(1) then replace the first two lines with the following:

  ```
  # setenv PKG_PATH ftp://ftp.NetBSD.org/pub/NetBSD/packages/4.0_RC2/amiga/All
  ...
  ```

  The above commands will install the Tenex-csh and Bourne Again shell, the Perl programming language, Apache web server, KDE desktop environment and the Firefox web browser as well as all the packages they depend on.
- Package sources for compiling packages on your own can be obtained by retrieving the file
  ftp://ftp.NetBSD.org/pub/NetBSD/NetBSD-current/tar_files/pkgsrc.tar.gz
  They are typically extracted into `/usr/pkgsrc` (though other locations work fine), with the commands:

  ```
  # mkdir /usr/pkgsrc
  # cd /usr/pkgsrc
  # tar -zxpf pkgsrc.tar.gz
  ```

  After extracting, see the `README` and `doc/pkgsrc.txt` files in the extraction directory (e.g. `/usr/pkgsrc/README`) for more information.

6. Misc
   - Edit `/etc/mail/aliases` to forward root mail to the right place. Don't forget to run `newaliases`(1) afterwards.
   - The `/etc/mail/sendmail.cf` file will almost definitely need to be adjusted; files aiding in this can be found in `/usr/share/sendmail`. See the `README` file there for more information. If you prefer postfix as MTA, adjust `/etc/mailer.conf`.
   - Edit `/etc/rc.local` to run any local daemons you use.
   - Many of the `/etc` files are documented in section 5 of the manual; so just invoking

```
# man 5 filename
```

is likely to give you more information on these files.

Upgrading a previously-installed NetBSD System

The upgrade to NetBSD 4.0_RC2 is a binary upgrade; it can be quite difficult to advance to a later version by recompiling from source due primarily to interdependencies in the various components.

To do the upgrade, you must have the NetBSD kernel on AmigaDOS and you must transfer the miniroot file system `miniroot.fs` onto the swap partition of the NetBSD hard disk. You must also have at least the **base** binary distribution set available, so that you can upgrade with it, using one of the upgrade methods described above. Finally, you must have sufficient disk space available to install the new binaries. Since the old binaries are being overwritten in place, you only need space for the new binaries, which weren't previously on the system. If you have a few megabytes free on each of your `/` (root) and `/usr` partitions, you should have enough space.

Since upgrading involves replacing the kernel, and most of the system binaries, it has the potential to cause data loss. You are strongly advised to BACK UP ANY IMPORTANT DATA ON YOUR DISK, whether on the NetBSD partition or on another operating system's partition, before beginning the upgrade process.

To upgrade your system, follow the following instructions:

Transfer the miniroot file system onto the hard disk partition used by NetBSD for swapping, as described in the "Preparing your System for NetBSD Installation" section above.

Now boot up NetBSD, with boot blocks installed

Note: This description is for V40 (OS 3.1) ROMs. For older ROMs, there might be small differences. Check your AmigaDOS documentation to learn about the exact procedure. Booting using bootblocks doesn't work at all on some systems, and may require a mountable file system on others.

Reboot your machine, holding down both mouse buttons if you have a 2-button mouse, the outer mouse buttons if you have a 3-button mouse. On the DraCo, press the left mouse button instead, when the boot screen prompts you for it.

From the boot menu, select **`Boot Options`**. Select the swap partition with the miniroot, and then **`ok`**. Select **`Boot`** now. The machine will boot the bootblock, which will prompt your for a command line. You have a few seconds time to change the default. Entering an empty line will accept the default.

The bootblock uses command lines of the form:

file [*options*]

where *file* is the kernel file name on the partition where the boot block is on, and *options* may contain the same as described in the INSTALL section.

For installing, use

`netbsd -b`

If you machine has a split memory space, like, e.g., DraCo machines, use this instead:

`netbsd -bn2`

Once your kernel boots

You should see the screen clear and some information about your system as the kernel configures the hardware. Note which hard disk device is configured that contains your root (`/`) and swap partitions. When prompted for the root device, type `sd0b` (replacing '`0`' with the disk number that NetBSD used for your root/swap device). When prompted for a dump device, answer '**`none`**' for the upgrade. (For a normal boot, you would tell it one of the swap devices). When prompted for the root file system type, confirm '**`generic`**', which will auto-detect it.

You will be presented with some information about the upgrade process and a warning message, and will be asked if you wish to proceed with the upgrade process. If you answer negatively, the upgrade process will stop, and your disk will not be modified. If you answer affirmatively, the upgrade process will begin, and your disk will be modified. You may press `CONTROL-C` to stop the upgrade process at any time. However, if you press it at an inopportune moment, your system may be left in an inconsistent (and possibly unusable) state.

You will now be greeted and reminded of the fact that this is a potential dangerous procedure and that you should not upgrade the **etc** set.

When you decide to proceed, you will be prompted to enter your root disk. After you've done this, it will be checked automatically to make sure that the file system is in a sane state before making any modifications. After this is done, you will be asked if you want to configure your network.

You are now allowed to edit your fstab. Normally you don't have to. Note that the upgrade-kit uses its own copy of the fstab. Whatever you do here *won't* affect your actual fstab. After you are satisfied with your fstab, the upgrade-kit will check all file systems mentioned in it. When they're ok, they will be mounted.

You will now be asked if your sets are stored on a normally mounted file system. You should answer '**`y`**' to this question if you have the sets stored on a file system that was present in the fstab. The actions you should take for the set extraction are pretty logical (we think).

After you have extracted the sets, the upgrade kit will proceed with setting the timezone and installing the kernel and bootcode. This is all exactly the same as described in the installation section.

Your system has now been upgraded to NetBSD 4.0_RC2.

After a new kernel has been copied to your hard disk, your machine is a complete NetBSD 4.0_RC2 system. However, that doesn't mean that you're finished with the upgrade process. There are several things that you should do, or might have to do, to insure that the system works properly.

You will probably want to get the **etc** distribution, extract it, and compare its contents with those in your `/etc` directory. You will probably want to replace some of your system configuration files, or incorporate some of the changes in the new versions into yours.

You will want to delete old binaries that were part of the version of NetBSD that you upgraded from and have since been removed from the NetBSD distribution. If upgrading from a NetBSD version older than 1.0, you might also want to recompile any locally-built binaries, to take advantage of the shared libraries. (Note that any new binaries that you build will be dynamically linked, and therefore take advantage of the shared libraries, by default. For information on how to make statically linked binaries, see the `cc`(1) and `ld`(1) manual pages.)

Compatibility Issues With Previous NetBSD Releases

Users upgrading from previous versions of NetBSD may wish to bear the following problems and compatibility issues in mind when upgrading to NetBSD 4.0_RC2 .

Issues affecting an upgrade from NetBSD 2.1 and older releases.

See the section below on upgrading from NetBSD 3.x as well.

It is **`very important`** that you populate the directory `/etc/pam.d` with appropriate configuration files for the Pluggable Authentication Modules (PAM) because you will not be able to login any more otherwise. Using *postinstall* as described below will take care of this. Please refer to

http://www.netbsd.org/guide/en/chap-pam.html

for documentation about PAM.

The following issues can generally be resolved by extracting the **etc** set into a temporary directory and running *postinstall*:

```
postinstall -s /path/to/etc.tgz check
postinstall -s /path/to/etc.tgz fix
```

Issues fixed by *postinstall*:

- Various files in `/etc` need upgrading. These include:
  - `/etc/defaults/*`
  - `/etc/mtree/*`
  - `/etc/pam.d/*`
  - `/etc/daily`
  - `/etc/weekly`
  - `/etc/monthly`
  - `/etc/security`
  - `/etc/rc.subr`
  - `/etc/rc`
  - `/etc/rc.shutdown`
  - `/etc/rc.d/*`

The following issues need to be resolved manually:

- The user '_pflogd' and the groups '_pflogd' and 'authpf' need to be created.

Issues affecting an upgrade from NetBSD 3.x releases.

The following issues can generally be resolved by extracting the **etc** set into a temporary directory and running *postinstall*:

```
postinstall -s /path/to/etc.tgz check
postinstall -s /path/to/etc.tgz fix
```

Issues fixed by *postinstall*:

- Various files in `/etc` need upgrading. These include:
  - `/etc/defaults/*`
  - `/etc/mtree/*`
  - `/etc/daily`
  - `/etc/weekly`
  - `/etc/monthly`
  - `/etc/security`
  - `/etc/rc.subr`
  - `/etc/rc`
  - `/etc/rc.shutdown`
  - `/etc/rc.d/*`
  - `/etc/envsys.conf`

The following issues need to be resolved manually:

- The users '_proxy' and 'authpf' and the groups '_proxy' and 'rwhod' need to be created and the user 'uucp' needs to be updated.
- A number of things have been removed from the NetBSD 4.0_RC2 release including: the evbsh5 port, the Fortran 77 compiler (g77), NETCCITT, NETNS, Sendmail, Sushi, UUCP, and Vinum. If you were using any of these, then please see the "Components removed from NetBSD" section near the beginning of this document.

Using online NetBSD documentation

Documentation is available if you first install the manual distribution set. Traditionally, the "man pages" (documentation) are denoted by '`name(section)`'. Some examples of this are

- `intro`(1),
- `man`(1),
- `apropos`(1),
- `passwd`(1), and
- `passwd`(5).

The section numbers group the topics into several categories, but three are of primary interest: user commands are in section 1, file formats are in section 5, and administrative information is in section 8.

The *man* command is used to view the documentation on a topic, and is started by entering **man** [*section*] *topic*. The brackets [] around the section should not be entered, but rather indicate that the section is optional. If you don't ask for a particular section, the topic with the lowest numbered section name will be displayed. For instance, after logging in, enter

```
# man passwd
```

to read the documentation for `passwd`(1). To view the documentation for `passwd`(5), enter

```
# man 5 passwd
```

instead.

If you are unsure of what man page you are looking for, enter

```
# apropos subject-word
```

where *subject-word* is your topic of interest; a list of possibly related man pages will be displayed.

Administrivia

If you've got something to say, do so! We'd like your input. There are various mailing lists available via the mailing list server at `majordomo@NetBSD.org`. To get help on using the mailing list server, send mail to that address with an empty body, and it will reply with instructions.

There are various mailing lists set up to deal with comments and questions about this release. Please send comments to: `netbsd-comments@NetBSD.org`.

To report bugs, use the `send-pr`(1) command shipped with NetBSD, and fill in as much information about the problem as you can. Good bug reports include lots of details. Additionally, bug reports can be sent by mail to: `netbsd-bugs@NetBSD.org`.

Use of `send-pr`(1) is encouraged, however, because bugs reported with it are entered into the NetBSD bugs database, and thus can't slip through the cracks.

There are also port-specific mailing lists, to discuss aspects of each port of NetBSD. Use majordomo to find their addresses, or visit **http://www.NetBSD.org/MailingLists/**. If you're interested in doing a serious amount of work on a specific port, you probably should contact the 'owner' of that port (listed below).

If you'd like to help with this effort, and have an idea as to how you could be useful, send us mail or subscribe to: `netbsd-help@NetBSD.org`.

As a favor, please avoid mailing huge documents or files to these mailing lists. Instead, put the material you would have sent up for FTP or WWW somewhere, then mail the appropriate list about it, or, if you'd rather not do that, mail the list saying you'll send the data to those who want it.

Thanks go to

- The former members of UCB's Computer Systems Research Group, including (but not limited to):

  Keith Bostic
  Ralph Campbell
  Mike Karels
  Marshall Kirk McKusick

  for their ongoing work on BSD systems, support, and encouragement.

- The Internet Systems Consortium, Inc. for hosting the NetBSD FTP, CVS, AnonCVS, mail, mail archive, GNATS, SUP, Rsync and WWW servers.
- The Internet Research Institute in Japan for hosting the server which runs the CVSweb interface to the NetBSD source tree.
- The Helsinki University of Technology in Finland for hosting the NetBSD backup CVS and backup server.
- SSH Communications Security in Finland for operating the backup server.
- The many organizations that provide NetBSD mirror sites.
- Without CVS, this project would be impossible to manage, so our hats go off to Brian Berliner, Jeff Polk, and the various other people who've had a hand in making CVS a useful tool.
- We list the individuals and organizations that have made donations or loans of hardware and/or money, to support NetBSD development, and deserve credit for it at *.:* **http://www.NetBSD.org/donations** (If you're not on that list and should be, tell us! We probably were not able to get in touch with you, to verify that you wanted to be listed.)
- Finally, we thank all of the people who've put sweat and tears into developing NetBSD since its inception in January, 1993. (Obviously, there are a lot more people who deserve thanks here. If you're one of them, and would like to mentioned, tell us!)

We are...

(in alphabetical order)

The NetBSD core group:

Alistair Crooks	`agc@NetBSD.org`
YAMAMOTO Takashi	`yamt@NetBSD.org`
Matt Thomas	`matt@NetBSD.org`
Valeriy E. Ushakov	`uwe@NetBSD.org`
Christos Zoulas	`christos@NetBSD.org`

The portmasters (and their ports):

Anders Magnusson	ragge	**vax**
Andrey Petrov	petrov	**sparc64**
Ben Harris	bjh21	**acorn26**
Cherry G. Mathew	cherry	**ia64**
Chris Gilbert	chris	**cats**
Darrin Jewell	dbj	**next68k**
Erik Berls	cyber	**cobalt**
Frank van der Linden	fvdl	**amd64**
Frank van der Linden	fvdl	**i386**
Gavan Fantom	gavan	**iyonix**
IWAMOTO Toshihiro	toshii	**hpcarm**
Ichiro FUKUHARA	ichiro	**hpcarm**
Ignatios Souvatzis	is	**amiga**
Izumi Tsutsui	tsutsui	**ews4800mips**
Izumi Tsutsui	tsutsui	**hp300**
Izumi Tsutsui	tsutsui	**news68k**
Jaime A Fournier	ober	**zaurus**
Jason Thorpe	thorpej	**algor**
Jason Thorpe	thorpej	**evbarm**
Jason Thorpe	thorpej	**shark**
Jonathan Stone	jonathan	**pmax**
Julian Coleman	jdc	**atari**
Manuel Bouyer	bouyer	**xen**
Marcus Comstedt	marcus	**dreamcast**
Martin Husemann	martin	**sparc64**
Matt Fredette	fredette	**sun2**
Matt Thomas	matt	**alpha**
Matt Thomas	matt	**netwinder**
Matthias Drochner	drochner	**cesfic**
Michael Lorenz	macallan	**macppc**
NISHIMURA Takeshi	nsmrtks	**x68k**
Nathan Williams	nathanw	**sun3**
Nick Hudson	skrll	**hp700**
Noriyuki Soda	soda	**arc**
Paul Kranenburg	pk	**sparc**
Phil Nelson	phil	**pc532**
Reinoud Zandijk	reinoud	**acorn32**
Ross Harvey	ross	**alpha**
Søren Jørvang	soren	**sgimips**
Scott Reynolds	scottr	**mac68k**
Shin Takemura	takemura	**hpcmips**
Simon Burge	simonb	**evbmips**
Simon Burge	simonb	**pmax**
Simon Burge	simonb	**sbmips**
Steve Woodford	scw	**evbppc**
Steve Woodford	scw	**mvme68k**
Steve Woodford	scw	**mvmeppc**

Takayoshi Kochi	kochi	**ia64**
Tim Rightnour	garbled	**prep**
Tohru Nishimura	nisimura	**luna68k**
Tohru Nishimura	nisimura	**sandpoint**
UCHIYAMA Yasushi	uch	**hpcsh**
UCHIYAMA Yasushi	uch	**playstation2**
Wayne Knowles	wdk	**mipsco**
Wolfgang Solfrank	ws **ofppc**	

The NetBSD 4.0_RC2 Release Engineering team:

Grant Beattie	grant@NetBSD.org
Manuel Bouyer	bouyer@NetBSD.org
David Brownlee	abs@NetBSD.org
Pavel Cahyna	pavel@NetBSD.org
James Chacon	jmc@NetBSD.org
Julian Coleman	jdc@NetBSD.org
Håvard Eidnes	he@NetBSD.org
Liam J. Foy	liamjfoy@NetBSD.org
John Heasley	heas@NetBSD.org
Geert Hendrickx	ghen@NetBSD.org
Soren Jacobsen	snj@NetBSD.org
Daniel de Kok	daniel@NetBSD.org
Phil Nelson	phil@NetBSD.org
Jeff Rizzo	riz@NetBSD.org

NetBSD Developers:

Nathan Ahlstrom	nra@NetBSD.org
Steve Allen	wormey@NetBSD.org
Jukka Andberg	jandberg@NetBSD.org
Julian Assange	proff@NetBSD.org
Lennart Augustsson	augustss@NetBSD.org
Christoph Badura	bad@NetBSD.org
Bang Jun-Young	junyoung@NetBSD.org
Dieter Baron	dillo@NetBSD.org
Robert V. Baron	rvb@NetBSD.org
Alan Barrett	apb@NetBSD.org
Grant Beattie	grant@NetBSD.org
Jason Beegan	jtb@NetBSD.org
Erik Berls	cyber@NetBSD.org
Hiroyuki Bessho	bsh@NetBSD.org
John Birrell	jb@NetBSD.org
Mason Loring Bliss	mason@NetBSD.org
Charles Blundell	cb@NetBSD.org
Rafal Boni	rafal@NetBSD.org
Stephen Borrill	sborrill@NetBSD.org
Sean Boudreau	seanb@NetBSD.org
Manuel Bouyer	bouyer@NetBSD.org

John Brezak	brezak@NetBSD.org
Allen Briggs	briggs@NetBSD.org
Mark Brinicombe	mark@NetBSD.org
Aaron Brown	abrown@NetBSD.org
Andrew Brown	atatat@NetBSD.org
David Brownlee	abs@NetBSD.org
Frederick Bruckman	fredb@NetBSD.org
Jon Buller	jonb@NetBSD.org
Simon Burge	simonb@NetBSD.org
Robert Byrnes	byrnes@NetBSD.org
Pavel Cahyna	pavel@NetBSD.org
D'Arcy J.M. Cain	darcy@NetBSD.org
Dave Carrel	carrel@NetBSD.org
Daniel Carosone	dan@NetBSD.org
James Chacon	jmc@NetBSD.org
Bill Coldwell	billc@NetBSD.org
Julian Coleman	jdc@NetBSD.org
Ben Collver	ben@NetBSD.org
Jeremy Cooper	jeremy@NetBSD.org
Chuck Cranor	chuck@NetBSD.org
Alistair Crooks	agc@NetBSD.org
Aidan Cully	aidan@NetBSD.org
Garrett D'Amore	gdamore@NetBSD.org
Johan Danielsson	joda@NetBSD.org
John Darrow	jdarrow@NetBSD.org
Jed Davis	jld@NetBSD.org
Matt DeBergalis	deberg@NetBSD.org
Arnaud Degroote	degroote@NetBSD.org
Rob Deker	deker@NetBSD.org
Chris G. Demetriou	cgd@NetBSD.org
Tracy Di Marco White	gendalia@NetBSD.org
Jaromír Dolecek	jdolecek@NetBSD.org
Andy Doran	ad@NetBSD.org
Roland Dowdeswell	elric@NetBSD.org
Emmanuel Dreyfus	manu@NetBSD.org
Matthias Drochner	drochner@NetBSD.org
Jun Ebihara	jun@NetBSD.org
Håvard Eidnes	he@NetBSD.org
Stoned Elipot	seb@NetBSD.org
Michael van Elst	mlelstv@NetBSD.org
Enami Tsugutomo	enami@NetBSD.org
Bernd Ernesti	veego@NetBSD.org
Erik Fair	fair@NetBSD.org
Gavan Fantom	gavan@NetBSD.org
Hauke Fath	hauke@NetBSD.org
Hubert Feyrer	hubertf@NetBSD.org
Jason R. Fink	jrf@NetBSD.org
Matt J. Fleming	mjf@NetBSD.org
Liam J. Foy	liamjfoy@NetBSD.org

Matt Fredette	fredette@NetBSD.org
Thorsten Frueauf	frueauf@NetBSD.org
Castor Fu	castor@NetBSD.org
Ichiro Fukuhara	ichiro@NetBSD.org
Quentin Garnier	cube@NetBSD.org
Thomas Gerner	thomas@NetBSD.org
Simon J. Gerraty	sjg@NetBSD.org
Justin Gibbs	gibbs@NetBSD.org
Chris Gilbert	chris@NetBSD.org
Eric Gillespie	epg@NetBSD.org
Adam Glass	glass@NetBSD.org
Michael Graff	explorer@NetBSD.org
Brian C. Grayson	bgrayson@NetBSD.org
Matthew Green	mrg@NetBSD.org
Andreas Gustafsson	gson@NetBSD.org
Jun-ichiro itojun Hagino	itojun@NetBSD.org
Juergen Hannken-Illjes	hannken@NetBSD.org
Charles M. Hannum	mycroft@NetBSD.org
Ben Harris	bjh21@NetBSD.org
Ross Harvey	ross@NetBSD.org
Eric Haszlakiewicz	erh@NetBSD.org
John Hawkinson	jhawk@NetBSD.org
HAMAJIMA Katsuomi	hamajima@NetBSD.org
HAYAKAWA Koichi	haya@NetBSD.org
John Heasley	heas@NetBSD.org
Geert Hendrickx	ghen@NetBSD.org
René Hexel	rh@NetBSD.org
Iain Hibbert	plunky@NetBSD.org
Kouichirou Hiratsuka	hira@NetBSD.org
Michael L. Hitch	mhitch@NetBSD.org
Jachym Holecek	freza@NetBSD.org
Christian E. Hopps	chopps@NetBSD.org
Ken Hornstein	kenh@NetBSD.org
Marc Horowitz	marc@NetBSD.org
Eduardo Horvath	eeh@NetBSD.org
Nick Hudson	skrll@NetBSD.org
Shell Hung	shell@NetBSD.org
Martin Husemann	martin@NetBSD.org
Dean Huxley	dean@NetBSD.org
Love Hörnquist Åstrand	lha@NetBSD.org
Bernardo Innocenti	bernie@NetBSD.org
Tetsuya Isaki	isaki@NetBSD.org
ITOH Yasufumi	itohy@NetBSD.org
IWAMOTO Toshihiro	toshii@NetBSD.org
Matthew Jacob	mjacob@NetBSD.org
Soren Jacobsen	snj@NetBSD.org
Lonhyn T. Jasinskyj	lonhyn@NetBSD.org
Darrin Jewell	dbj@NetBSD.org
Nicolas Joly	njoly@NetBSD.org

Chris Jones	cjones@NetBSD.org
Søren Jørvang	soren@NetBSD.org
Takahiro Kambe	taca@NetBSD.org
Antti Kantee	pooka@NetBSD.org
Masanori Kanaoka	kanaoka@NetBSD.org
Frank Kardel	kardel@NetBSD.org
Mattias Karlsson	keihan@NetBSD.org
KAWAMOTO Yosihisa	kawamoto@NetBSD.org
Mario Kemper	magick@NetBSD.org
Min Sik Kim	minskim@NetBSD.org
Thomas Klausner	wiz@NetBSD.org
Klaus Klein	kleink@NetBSD.org
John Klos	jklos@NetBSD.org
Wayne Knowles	wdk@NetBSD.org
Takayoshi Kochi	kochi@NetBSD.org
John Kohl	jtk@NetBSD.org
Daniel de Kok	daniel@NetBSD.org
Paul Kranenburg	pk@NetBSD.org
Lubomir Kundrak	lkundrak@NetBSD.org
Martti Kuparinen	martti@NetBSD.org
Kentaro A. Kurahone	kurahone@NetBSD.org
Kevin Lahey	kml@NetBSD.org
David Laight	dsl@NetBSD.org
Johnny C. Lam	jlam@NetBSD.org
Martin J. Laubach	mjl@NetBSD.org
Greg Lehey	grog@NetBSD.org
Ted Lemon	mellon@NetBSD.org
Christian Limpach	cl@NetBSD.org
Frank van der Linden	fvdl@NetBSD.org
Joel Lindholm	joel@NetBSD.org
Mike Long	mikel@NetBSD.org
Michael Lorenz	macallan@NetBSD.org
Warner Losh	imp@NetBSD.org
Tomasz Luchowski	zuntum@NetBSD.org
Federico Lupi	federico@NetBSD.org
Brett Lymn	blymn@NetBSD.org
Paul Mackerras	paulus@NetBSD.org
Anders Magnusson	ragge@NetBSD.org
MAEKAWA Masahide	gehenna@NetBSD.org
David Maxwell	david@NetBSD.org
Dan McMahill	dmcmahill@NetBSD.org
Gregory McGarry	gmcgarry@NetBSD.org
Jared D. McNeill	jmcneill@NetBSD.org
Neil J. McRae	neil@NetBSD.org
Perry Metzger	perry@NetBSD.org
Simas Mockevicius	symka@NetBSD.org
Juan Romero Pardines	xtraeme@NetBSD.org
Julio M. Merino Vidal	jmmv@NetBSD.org
Minoura Makoto	minoura@NetBSD.org

Luke Mewburn	lukem@NetBSD.org
der Mouse	mouse@NetBSD.org
Joseph Myers	jsm@NetBSD.org
Ken Nakata	kenn@NetBSD.org
Takeshi Nakayama	nakayama@NetBSD.org
Phil Nelson	phil@NetBSD.org
John Nemeth	jnemeth@NetBSD.org
Bob Nestor	rnestor@NetBSD.org
NISHIMURA Takeshi	nsmrtks@NetBSD.org
Tohru Nishimura	nisimura@NetBSD.org
NONAKA Kimihiro	nonaka@NetBSD.org
Takehiko NOZAKI	tnozaki@NetBSD.org
Tobias Nygren	tnn@NetBSD.org
OBATA Akio	obache@NetBSD.org
Jesse Off	joff@NetBSD.org
Tatoku Ogaito	tacha@NetBSD.org
OKANO Takayoshi	kano@NetBSD.org
Masaru Oki	oki@NetBSD.org
Atsushi Onoe	onoe@NetBSD.org
Greg Oster	oster@NetBSD.org
Jonathan Perkin	sketch@NetBSD.org
Herb Peyerl	hpeyerl@NetBSD.org
Matthias Pfaller	matthias@NetBSD.org
Chris Pinnock	cjep@NetBSD.org
Adrian Portelli	adrianp@NetBSD.org
Rui Paulo	rpaulo@NetBSD.org
Peter Postma	peter@NetBSD.org
Dante Profeta	dante@NetBSD.org
Chris Provenzano	proven@NetBSD.org
Niels Provos	provos@NetBSD.org
Mindaugas Rasiukevicius	rmind@NetBSD.org
Michael Rauch	mrauch@NetBSD.org
Marc Recht	recht@NetBSD.org
Darren Reed	darrenr@NetBSD.org
Jeremy C. Reed	reed@NetBSD.org
Antoine Reilles	tonio@NetBSD.org
Tyler R. Retzlaff	rtr@NetBSD.org
Scott Reynolds	scottr@NetBSD.org
Michael Richardson	mcr@NetBSD.org
Tim Rightnour	garbled@NetBSD.org
Alan Ritter	rittera@NetBSD.org
Jeff Rizzo	riz@NetBSD.org
Gordon Ross	gwr@NetBSD.org
Steve Rumble	rumble@NetBSD.org
Ilpo Ruotsalainen	lonewolf@NetBSD.org
Heiko W. Rupp	hwr@NetBSD.org
David Sainty	dsainty@NetBSD.org
SAITOH Masanobu	msaitoh@NetBSD.org
Kazuki Sakamoto	sakamoto@NetBSD.org

Curt Sampson	cjs@NetBSD.org
Wilfredo Sanchez	wsanchez@NetBSD.org
Ty Sarna	tsarna@NetBSD.org
SATO Kazumi	sato@NetBSD.org
Jan Schaumann	jschauma@NetBSD.org
Matthias Scheler	tron@NetBSD.org
Karl Schilke (rAT)	rat@NetBSD.org
Amitai Schlair	schmonz@NetBSD.org
Konrad Schroder	perseant@NetBSD.org
Georg Schwarz	schwarz@NetBSD.org
Lubomir Sedlacik	salo@NetBSD.org
Christopher SEKIYA	sekiya@NetBSD.org
Reed Shadgett	dent@NetBSD.org
John Shannon	shannonjr@NetBSD.org
Tim Shepard	shep@NetBSD.org
Takeshi Shibagaki	shiba@NetBSD.org
Naoto Shimazaki	igy@NetBSD.org
Takao Shinohara	shin@NetBSD.org
Takuya SHIOZAKI	tshiozak@NetBSD.org
Daniel Sieger	dsieger@NetBSD.org
Chuck Silvers	chs@NetBSD.org
Thor Lancelot Simon	tls@NetBSD.org
Jeff Smith	jeffs@NetBSD.org
Noriyuki Soda	soda@NetBSD.org
Wolfgang Solfrank	ws@NetBSD.org
T K Spindler	dogcow@NetBSD.org
SOMEYA Yoshihiko	someya@NetBSD.org
Bill Sommerfeld	sommerfeld@NetBSD.org
Jörg Sonnenberger	joerg@NetBSD.org
Ignatios Souvatzis	is@NetBSD.org
Bill Squier	groo@NetBSD.org
Jonathan Stone	jonathan@NetBSD.org
Bill Studenmund	wrstuden@NetBSD.org
Kevin Sullivan	sullivan@NetBSD.org
SUNAGAWA Keiki	kei@NetBSD.org
Kimmo Suominen	kim@NetBSD.org
Shin Takemura	takemura@NetBSD.org
TAMURA Kent	kent@NetBSD.org
Shin'ichiro TAYA	taya@NetBSD.org
Ian Lance Taylor	ian@NetBSD.org
Matt Thomas	matt@NetBSD.org
Jason Thorpe	thorpej@NetBSD.org
Christoph Toshok	toshok@NetBSD.org
Greg Troxel	gdt@NetBSD.org
Tsubai Masanari	tsubai@NetBSD.org
Izumi Tsutsui	tsutsui@NetBSD.org
UCHIYAMA Yasushi	uch@NetBSD.org
Masao Uebayashi	uebayasi@NetBSD.org
Shuichiro URATA	ur@NetBSD.org

Valeriy E. Ushakov	uwe@NetBSD.org
Todd Vierling	tv@NetBSD.org
Aymeric Vincent	aymeric@NetBSD.org
Paul Vixie	vixie@NetBSD.org
Mike M. Volokhov	mishka@NetBSD.org
Krister Walfridsson	kristerw@NetBSD.org
Lex Wennmacher	wennmach@NetBSD.org
Leo Weppelman	leo@NetBSD.org
Assar Westerlund	assar@NetBSD.org
Todd Whitesel	toddpw@NetBSD.org
Nathan Williams	nathanw@NetBSD.org
Rob Windsor	windsor@NetBSD.org
Dan Winship	danw@NetBSD.org
Arnaud Lacombe	alc@NetBSD.org
Jim Wise	jwise@NetBSD.org
Michael Wolfson	mbw@NetBSD.org
Steve Woodford	scw@NetBSD.org
Colin Wood	ender@NetBSD.org
YAMAMOTO Takashi	yamt@NetBSD.org
Yuji Yamano	yyamano@NetBSD.org
Reinoud Zandijk	reinoud@NetBSD.org
S.P.Zeidler	spz@NetBSD.org
Maria Zevenhoven	maria7@NetBSD.org
Christos Zoulas	christos@NetBSD.org

Other contributors:

Dave Burgess	burgess@cynjut.infonet.net
Brian R. Gaeke	brg@dgate.org
Brad Grantham	grantham@tenon.com
Lawrence Kesteloot	kesteloo@cs.unc.edu
Waldi Ravens	waldi@moacs.indiv.nl.net

Legal Mumbo-Jumbo

All product names mentioned herein are trademarks or registered trademarks of their respective owners.

The following notices are required to satisfy the license terms of the software that we have mentioned in this document:

NetBSD is a registered trademark of The NetBSD Foundation, Inc.
This product includes software developed by the University of California, Berkeley and its contributors.
This product includes software developed by the NetBSD Foundation.
This product includes software developed by The NetBSD Foundation, Inc. and its contributors.
This product includes software developed for the NetBSD Project. See http://www.netbsd.org/ for information about NetBSD.
This product contains software developed by Ignatios Souvatzis for the NetBSD project.
This product contains software written by Ignatios Souvatzis and Michael L. Hitch for the NetBSD project.
This product contains software written by Michael L. Hitch for the NetBSD project.
This product includes cryptographic software written by Eric Young (eay@cryptsoft.com)
This product includes cryptographic software written by Eric Young (eay@mincom.oz.au)
This product includes software designed by William Allen Simpson.
This product includes software developed at Ludd, University of Lulea, Sweden and its contributors.
This product includes software developed at Ludd, University of Lulea.
This product includes software developed at the Information Technology Division, US Naval Research Laboratory.
This product includes software developed by Berkeley Software Design, Inc.
This product includes software developed by David Jones and Gordon Ross

This product includes software developed by Gordon W. Ross and Leo Weppelman.
This product includes software developed by Hellmuth Michaelis and Joerg Wunsch
This product includes software developed by Internet Research Institute, Inc.
This product includes software developed by Leo Weppelman and Waldi Ravens.
This product includes software developed by Mika Kortelainen
This product includes software developed by Aaron Brown and Harvard University.
This product includes software developed by Adam Ciarcinski for the NetBSD project.
This product includes software developed by Adam Glass and Charles M. Hannum.
This product includes software developed by Adam Glass.
This product includes software developed by Advanced Risc Machines Ltd.
This product includes software developed by Alex Zepeda, and Colin Wood for the NetBSD Projet.
This product includes software developed by Alex Zepeda.
This product includes software developed by Alistair G. Crooks.
This product includes software developed by Alistair G. Crooks. for the NetBSD project.
This product includes software developed by Allen Briggs
This product includes software developed by Amancio Hasty and Roger Hardiman
This product includes software developed by Berkeley Software Design, Inc.
This product includes software developed by Berkeley Software Design, Inc.
This product includes software developed by Bill Paul.
This product includes software developed by Bodo Moeller. (If available, substitute umlauted o for oe)
This product includes software developed by Boris Popov.
This product includes software developed by Brad Pepers
This product includes software developed by Bradley A. Grantham.
This product includes software developed by Brini.
This product includes software developed by Causality Limited.
This product includes software developed by Charles D. Cranor and Seth Widoff.
This product includes software developed by Charles D. Cranor and Washington University.
This product includes software developed by Charles D. Cranor, Washington University, and the University of California, Berkeley and its contributors.
This product includes software developed by Charles D. Cranor, Washington University, the University of California, Berkeley and its contributors.
This product includes software developed by Charles D. Cranor.
This product includes software developed by Charles Hannum.
This product includes software developed by Charles M. Hannum, by the University of Vermont and State Agricultural College and Garrett A. Wollman, by William F. Jolitz, and by the University of California, Berkeley, Lawrence Berkeley Laboratory, and its contributors.
This product includes software developed by Charles M. Hannum.
This product includes software developed by Christian E. Hopps, Ezra Story, Kari Mettinen, Markus Wild, Lutz Vieweg and Michael Teske.
This product includes software developed by Christian E. Hopps.
This product includes software developed by Christian Limpach
This product includes software developed by Christopher G. Demetriou for the NetBSD Project.
This product includes software developed by Christopher G. Demetriou.
This product includes software developed by Christos Zoulas.
This product includes software developed by Chuck Silvers.
This product includes software developed by Colin Wood for the NetBSD Project.
This product includes software developed by Colin Wood.
This product includes software developed by Cybernet Corporation and Nan Yang Computer Services Limited
This product includes software developed by Daishi Kato
This product includes software developed by Dale Rahn.
This product includes software developed by Daniel Widenfalk and Michael L. Hitch.
This product includes software developed by Daniel Widenfalk for the NetBSD Project.
This product includes software developed by Darrin B. Jewell
This product includes software developed by David Miller.
This product includes software developed by Dean Huxley.
This product includes software developed by Eduardo Horvath.
This product includes software developed by Eric S. Hvozda.
This product includes software developed by Eric S. Raymond
This product includes software developed by Eric Young (eay@@mincom.oz.au)
This product includes software developed by Eric Young (eay@cryptsoft.com)
This product includes software developed by Eric Young (eay@mincom.oz.au)
This product includes software developed by Ezra Story and by Kari Mettinen.
This product includes software developed by Ezra Story, by Kari Mettinen and by Bernd Ernesti.
This product includes software developed by Ezra Story, by Kari Mettinen, Michael Teske and by Bernd Ernesti.
This product includes software developed by Ezra Story, by Kari Mettinen, and Michael Teske.
This product includes software developed by Ezra Story.

This product includes software developed by Frank van der Linden for the NetBSD Project.
This product includes software developed by Gardner Buchanan.
This product includes software developed by Gary Thomas.
This product includes software developed by Gordon Ross
This product includes software developed by Gordon W. Ross
This product includes software developed by HAYAKAWA Koichi.
This product includes software developed by Harvard University and its contributors.
This product includes software developed by Harvard University.
This product includes software developed by Herb Peyerl.
This product includes software developed by Hubert Feyrer for the NetBSD Project.
This product includes software developed by Iain Hibbert
This product includes software developed by Ian F. Darwin and others.
This product includes software developed by Ian W. Dall.
This product includes software developed by Ichiro FUKUHARA.
This product includes software developed by Ignatios Souvatzis for the NetBSD Project.
This product includes software developed by Internet Initiative Japan Inc.
This product includes software developed by James R. Maynard III.
This product includes software developed by Jared D. McNeill.
This product includes software developed by Jason L. Wright
This product includes software developed by Jason R. Thorpe for And Communications, http://www.and.com/
This product includes software developed by Joachim Koenig-Baltes.
This product includes software developed by Jochen Pohl for The NetBSD Project.
This product includes software developed by Joerg Wunsch
This product includes software developed by John Birrell.
This product includes software developed by John P. Wittkoski.
This product includes software developed by John Polstra.
This product includes software developed by Jonathan R. Stone for the NetBSD Project.
This product includes software developed by Jonathan Stone and Jason R. Thorpe for the NetBSD Project.
This product includes software developed by Jonathan Stone.
This product includes software developed by Juan Romero Pardines for the NetBSD Foundation, Inc. and its contributors.
This product includes software developed by Jukka Marin.
This product includes software developed by Julian Highfield.
This product includes software developed by Kazuhisa Shimizu.
This product includes software developed by Kazuki Sakamoto.
This product includes software developed by Kenneth Stailey.
This product includes software developed by Kiyoshi Ikehara.
This product includes software developed by Klaus Burkert,by Bernd Ernesti, by Michael van Elst, and by the University of California, Berkeley and its contributors.
This product includes software developed by LAN Media Corporation and its contributors.
This product includes software developed by Leo Weppelman for the NetBSD Project.
This product includes software developed by Leo Weppelman.
This product includes software developed by Lloyd Parkes.
This product includes software developed by Luke Mewburn.
This product includes software developed by Lutz Vieweg.
This product includes software developed by MINOURA Makoto, Takuya Harakawa.
This product includes software developed by Manuel Bouyer.
This product includes software developed by Marc Horowitz.
This product includes software developed by Marcus Comstedt.
This product includes software developed by Mark Brinicombe for the NetBSD project.
This product includes software developed by Mark Brinicombe.
This product includes software developed by Mark Murray
This product includes software developed by Mark Tinguely and Jim Lowe
This product includes software developed by Markus Wild.
This product includes software developed by Martin Husemann and Wolfgang Solfrank.
This product includes software developed by Masanobu Saitoh.
This product includes software developed by Masaru Oki.
This product includes software developed by Mats O Jansson and Charles D. Cranor.
This product includes software developed by Mats O Jansson.
This product includes software developed by Matt DeBergalis
This product includes software developed by Matthew Fredette.
This product includes software developed by Matthias Pfaller.
This product includes software developed by Michael Graff for the NetBSD Project.
This product includes software developed by Michael Graff.
This product includes software developed by Michael L. Hitch.
This product includes software developed by Michael Shalayeff.
This product includes software developed by Michael Smith.

This product includes software developed by Mike Glover and contributors.
This product includes software developed by Mike Pritchard.
This product includes software developed by Minoura Makoto.
This product includes software developed by Nan Yang Computer Services Limited.
This product includes software developed by Niels Provos.
This product includes software developed by Niklas Hallqvist, Brandon Creighton and Job de Haas.
This product includes software developed by Niklas Hallqvist.
This product includes software developed by Onno van der Linden.
This product includes software developed by Paul Kranenburg.
This product includes software developed by Paul Mackerras.
This product includes software developed by Per Fogelstrom
This product includes software developed by Peter Galbavy.
This product includes software developed by Phase One, Inc.
This product includes software developed by Philip A. Nelson.
This product includes software developed by Philip L. Budne.
This product includes software developed by RiscBSD.
This product includes software developed by Roar Thronæs.
This product includes software developed by Rodney W. Grimes.
This product includes software developed by Roger Hardiman
This product includes software developed by Roland C. Dowdeswell.
This product includes software developed by Rolf Grossmann.
This product includes software developed by Ross Harvey for the NetBSD Project.
This product includes software developed by Ross Harvey.
This product includes software developed by Scott Bartram.
This product includes software developed by Scott Stevens.
This product includes software developed by Shingo WATANABE.
This product includes software developed by Softweyr LLC, the University of California, Berkeley, and its contributors.
This product includes software developed by Soren S. Jorvang.
This product includes software developed by Stephan Thesing.
This product includes software developed by Steve Woodford.
This product includes software developed by Takashi Hamada
This product includes software developed by Takumi Nakamura.
This product includes software developed by Tatoku Ogaito for the NetBSD Project.
This product includes software developed by Terrence R. Lambert.
This product includes software developed by Tetsuya Isaki.
This product includes software developed by Thomas Gerner
This product includes software developed by Thomas Klausner for the NetBSD Project.
This product includes software developed by Tobias Weingartner.
This product includes software developed by Todd C. Miller.
This product includes software developed by Tohru Nishimura and Reinoud Zandijk for the NetBSD Project.
This product includes software developed by Tohru Nishimura for the NetBSD Project.
This product includes software developed by Tohru Nishimura. for the NetBSD Project.
This product includes software developed by TooLs GmbH.
This product includes software developed by Toru Nishimura.
This product includes software developed by Trimble Navigation, Ltd.
This product includes software developed by WIDE Project and its contributors.
This product includes software developed by Waldi Ravens.
This product includes software developed by Wasabi Systems for Zembu Labs, Inc. http://www.zembu.com/
This product includes software developed by Winning Strategies, Inc.
This product includes software developed by Wolfgang Solfrank.
This product includes software developed by Yasushi Yamasaki
This product includes software developed by Zembu Labs, Inc.
This product includes software developed by the Alice Group.
This product includes software developed by the Center for Software Science at the University of Utah.
This product includes software developed by the Charles D. Cranor, Washington University, University of California, Berkeley and its contributors.
This product includes software developed by the Computer Systems Engineering Group at Lawrence Berkeley Laboratory.
This product includes software developed by the David Muir Sharnoff.
This product includes software developed by the Harvard University and its contributors.
This product includes software developed by the Kungliga Tekniska Högskolan and its contributors.
This product includes software developed by the Network Research Group at Lawrence Berkeley Laboratory.
This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit. (http://www.OpenSSL.org/)
This product includes software developed by the PocketBSD project and its contributors.
This product includes software developed by the RiscBSD kernel team
This product includes software developed by the RiscBSD team.
This product includes software developed by the SMCC Technology Development Group at Sun Microsystems, Inc.

This product includes software developed by the University of California, Berkeley and its contributors, as well as the Trustees of Columbia University.
This product includes software developed by the University of California, Lawrence Berkeley Laboratory and its contributors.
This product includes software developed by the University of California, Lawrence Berkeley Laboratory.
This product includes software developed by the University of Illinois at Urbana and their contributors.
This product includes software developed by the University of Vermont and State Agricultural College and Garrett A. Wollman.
This product includes software developed by the University of Vermont and State Agricultural College and Garrett A. Wollman, by William F. Jolitz, and by the University of California, Berkeley, Lawrence Berkeley Laboratory, and its contributors.
This product includes software developed for the FreeBSD project
This product includes software developed for the NetBSD Project by Bernd Ernesti.
This product includes software developed for the NetBSD Project by Christopher G. Demetriou.
This product includes software developed for the NetBSD Project by Christos Zoulas
This product includes software developed for the NetBSD Project by Emmanuel Dreyfus.
This product includes software developed for the NetBSD Project by Frank van der Linden
This product includes software developed for the NetBSD Project by Ignatios Souvatzis.
This product includes software developed for the NetBSD Project by Jason R. Thorpe.
This product includes software developed for the NetBSD Project by John M. Vinopal.
This product includes software developed for the NetBSD Project by Matthias Drochner.
This product includes software developed for the NetBSD Project by Michael L. Hitch.
This product includes software developed for the NetBSD Project by Perry E. Metzger.
This product includes software developed for the NetBSD Project by Scott Bartram and Frank van der Linden
This product includes software developed for the NetBSD Project by Allegro Networks, Inc., and Wasabi Systems, Inc.
This product includes software developed for the NetBSD Project by Genetec Corporation.
This product includes software developed for the NetBSD Project by Jonathan Stone.
This product includes software developed for the NetBSD Project by Piermont Information Systems Inc.
This product includes software developed for the NetBSD Project by SUNET, Swedish University Computer Network.
This product includes software developed for the NetBSD Project by Shigeyuki Fukushima.
This product includes software developed for the NetBSD Project by Wasabi Systems, Inc.
This product includes software developed under OpenBSD by Per Fogelstrom Opsycon AB for RTMX Inc, North Carolina, USA.
This product includes software developed under OpenBSD by Per Fogelstrom.
This software is a component of "386BSD" developed by William F. Jolitz, TeleMuse.
This software was developed by Holger Veit and Brian Moore for use with "386BSD" and similar operating systems. "Similar operating systems" includes mainly non-profit oriented systems for research and education, including but not restricted to "NetBSD", "FreeBSD", "Mach" (by CMU).
This software includes software developed by the Computer Systems Laboratory at the University of Utah.
This product includes software developed by Computing Services at Carnegie Mellon University (http://www.cmu.edu/computing/).
This product includes software developed by Marshall M. Midden.
This product includes software developed or owned by Caldera International, Inc.
The Institute of Electrical and Electronics Engineers and The Open Group, have given us permission to reprint portions of their documentation.

In the following statement, the phrase ‘‘this text’’ refers to portions of the system documentation.

Portions of this text are reprinted and reproduced in electronic form in NetBSD, from IEEE Std 1003.1, 2004 Edition, Standard for Information Technology -- Portable Operating System Interface (POSIX), The Open Group Base Specifications Issue 6, Copyright (C) 2001-2004 by the Institute of Electrical and Electronics Engineers, Inc and The Open Group. In the event of any discrepancy between these versions and the original IEEE and The Open Group Standard, the original IEEE and The Open Group Standard is the referee document.

The original Standard can be obtained online at http://www.opengroup.org/unix/online.html.

This notice shall appear on any product containing this material

This product includes software developed by Tobias Abt.
This product includes software developed by Klaus Burkert.
This product includes software developed by Michael van Elst.
This product includes software developed by Bernd Ernesti.
This product includes software developed by Markus Illenseer.
This product includes software developed by Mika Kortelainen.
This product includes software developed by Jukka Marin.
This product includes software developed by Kari Mettinen.
This product includes software developed by Brad Pepers.
This product includes software developed by Ignatios Souvatzis.
This product includes software developed by Michael Teske.
This product includes software developed by Lutz Vieweg.
This product includes software developed by Daniel Widenfalk.

The End